

Installation Procedure

Firmware Upgrade for PSR-1500 & PSR-3000

Caution:

Do not turn the instrument off while installing. Do not take the Smartmedia card out from the instrument while installing.

1. Download the Zip file.
2. Extract the six files included in the Zip file.
3. Insert Smartmedia card into your computer or external Smartmedia card reader.
4. Copy extracted files into root directory of Smartmedia.



5. Insert Smartmedia into the instrument (gold side down).




6. Turn on the instrument while pressing [START/STOP] button, located in the style control section.




7. The installation will start automatically. Follow the instructions shown on the instrument's LCD screen.

Appearance of instructions may vary slightly depending on your instrument's screen type.


Screen 1



Screen 2



Screen 3



8. Restart the instrument.
9. Installation of the Firmware Upgrade is complete.